



OPERATOR DOCUMENTATION

Brand-neutral reference



# Deterministic Broadcast Console

## Operator User Manual

Brand-neutral edition | Version 1.0

A visual, task-focused guide for safe mouse-driven broadcast operation.

CONTROL. VERIFY. BROADCAST.

## PURPOSE AND SAFETY

# Designed for operator authority

The console is deterministic: the person at the workstation decides when a stream starts, stops, changes source, or changes automation.

## 01

### Explicit actions

Broadcast state changes require a visible mouse action and a verified result.

## 02

### Queue continuity

A normal stop preserves order. Resume restarts the interrupted item from the beginning.

## 03

### Scoped settings

Media, automation, output, and optional services are configured per station profile.

**SAFETY**

### The three checks before any state change

Confirm the selected station profile, confirm the visible current status, and confirm the action result. Never infer success from a button press alone.

### ● SELECT

Choose the intended station profile.



### ● ACT

Click the required control.



### ● VERIFY

Read the returned status and timeline.

NAVIGATION

# Contents

Use this manual during onboarding, live operation, and incident recovery.

|                                   |    |
|-----------------------------------|----|
| Interface tour                    | 04 |
| Start-of-shift readiness          | 05 |
| Start, stop, and queue continuity | 06 |
| Managed media and queue           | 07 |
| Adjustable automation             | 08 |
| Priority external audio           | 09 |
| Output settings                   | 10 |
| System health                     | 11 |
| Daily operating checklist         | 12 |
| Troubleshooting                   | 13 |
| Glossary                          | 14 |
| Quick reference                   | 15 |

GUIDE


Reading pattern

Every task page follows the same sequence: goal, annotated interface, exact mouse actions, and a visible verification point.

## ORIENTATION

# A consistent control surface

The neutral example below shows the standard pattern without organization-specific names, endpoints, or integrations.



- 1 Workspace navigation groups tasks by purpose.
- 2 System-ready badge confirms application connectivity.
- 3 Live state remains visible inside the active workspace.
- 4 Primary actions use explicit verbs and a visible result.

## DESIGN

## No hidden control path

Normal broadcast operation is available entirely through the visible interface. Automation does not replace operator authorization.

## START OF SHIFT

# Five-minute readiness routine

Complete this sequence at the beginning of every operating period and after any restart.

1

**Sign in locally**

Use your assigned operator account. Do not share passwords or leave a signed-in console unattended.

2

**Select the station**

Read the active station label at the top of the screen before touching broadcast controls.

3

**Open Health or Diagnostics**

Confirm the application, media tools, station profile, monitor, and stream destination.

4

**Review Media and Automation**

Confirm the managed folder, pending queue, insert interval, and selection order.

5

**Return to On Air**

Read the current state. Start or resume only when the scheduled program should be live.


**CHECK****A green connection badge is necessary, not sufficient**

The backend may be reachable while a station output or local monitor still needs attention. The readiness page is the authoritative checklist.

## CORE OPERATION

# Start, stop, and keep the queue

A normal stop is a controlled pause, not a playlist reset.



- 1 Read the live state first.
- 2 Confirm the current item and timeline.
- 3 Stop requires a deliberate confirmation and preserves the queue.
- 4 Start / resume restarts the interrupted item from the beginning.


**VERIFY****Expected stop result**

The live badge changes to off, the engine and scheduler stop, and the pending queue remains in the same order.

LIBRARY AND QUEUE

# Import only the intended program library

Use the native folder picker, define scope, sync, and verify before adding tracks.



- 1

Managed folder is visible before scanning.
- 2

Browse opens the operating-system picker.
- 3

Library rows show what is available.
- 4

Add one intended item to the queue.

VERIFY


After each queue edit

Wait for the refreshed order, then read the next item and forecast. Do not make a second edit while the first result is unknown.

DETERMINISTIC RULES

# Choose the insert interval

Automatic jingles are optional. Set the number of completed songs between inserts and choose the selection order.



- 1

Enable or disable the rule.
- 2

Enter 2, 3, or another allowed interval.
- 3

Choose random or rotation order.
- 4

Save and verify the returned rule.

VERIFY

### How the counter works


Only completed songs count. An interrupted song does not increment the interval until it finishes, and the current song finishes before the insert plays.



EXTERNAL SOURCE

# Take over with approved browser-tab audio

Preview the source, share only its tab audio, arm the takeover, and verify the returned signal.



- 1 Enter an approved HTTP or HTTPS page.
- 2 Preview and confirm shared tab audio.
- 3 Arm the priority takeover.
- 4 Restore normal audio when the event ends.

VERIFY


**Safe source rule**

Use only approved official sources. If the source is silent or unclear, restore normal program audio and follow the authorized fallback procedure.

OUTPUT

# Save, apply, test

Output settings are scoped to the selected profile and should be changed only with a verification plan.



- 1

Confirm the profile identity.
- 2

Adjust gain conservatively.
- 3

Enable only the intended output path.
- 4

Save, apply, and verify before testing.

VERIFY

### Protect credentials

Keep stream passwords and tokens only in protected input fields. Remove organization-specific details from screenshots and support reports.

READINESS

# Resolve required checks before live use

The health page is the authoritative view of application, media, profile, monitor, and output readiness.



1

Green means ready.

2

Amber means optional or review.

3

Red means operator action is required.

4

Re-run checks after each correction.

VERIFY


## Production gate

Do not start while a required media, profile, or output check is red. Optional features may remain disabled when core playout is healthy.

## ROUTINE

# A complete mouse-driven shift

Use the same predictable sequence at startup, during operation, and at handover.



## Before live

- Select the intended profile.
- Confirm ready status.
- Review queue and inserts.
- Confirm monitor and output.

## While live

- Watch current item and forecast.
- Edit one queue item at a time.
- Use two-step stop.
- Keep priority audio off unless authorized.

## At handover

- State live status.
- List next queue items.
- Record warnings.
- Lock or sign out.

RECOVERY

# Symptom-to-action matrix

Use visible status and bounded corrective actions. Do not repeatedly click a control while the result is unknown.

| SYMPTOM                      | OPERATOR ACTION                                                              | VERIFICATION                            |
|------------------------------|------------------------------------------------------------------------------|-----------------------------------------|
| Dashboard will not open      | Wait for startup, then reopen the tray action.                               | Login screen or readiness page appears. |
| Stream rejected              | Recheck destination, mount, user, password, and codec; run destination test. | Test reports accepted.                  |
| Media missing                | Confirm folder access; sync and verify; review unreadable files.             | Expected library count appears.         |
| Jingle did not run           | Check enabled state, interval, completed-song count, and selection order.    | Verified rule appears in activity.      |
| Priority audio is silent     | Select the correct browser tab and enable shared tab audio.                  | Signal and buffer become active.        |
| Optional service unavailable | Disable it, preserve music continuity, then run service health.              | Core playlist remains healthy.          |

ESCALATE

Escalate with evidence

Record the time, selected station, visible status, exact action, and exact error. Remove credentials and organization-specific details before sharing.

## TERMS

# Glossary and operating language

Consistent language helps operators make precise decisions.

**Station profile**

A self-contained set of media, queue, automation, output, and monitor settings.

**Managed folder**

The approved file-system location used to build one profile's media library.

**Queue**

The ordered list of pending program items.

**Current item**

The item playing now or waiting to restart after a preserved stop.

**Insert interval**

The number of completed songs between automatic jingles or other configured inserts.

**Priority audio**

Approved external browser-tab audio that temporarily replaces normal program audio.

**Readiness check**

A visible list of required, optional, ready, warning, and failed components.

**Verified action**

A control action followed by a returned state that confirms the intended result.

**PRIVACY****Document boundary**

This edition intentionally contains no organization-specific branding, station names, server addresses, mount labels, credentials, or private service details.

## ONE PAGE

# Operator quick reference

The shortest safe path for common actions.

**START**

Select station -> On Air -> read state -> Start / resume -> verify ON AIR

**STOP**

On Air -> Stop -> Confirm within 20 seconds -> verify OFF AIR and unchanged queue

**IMPORT**

Media -> Browse -> choose folder -> set scope -> Sync and verify

**JINGLES**

Automation -> enable -> set song interval -> choose order -> Save and verify

**PRIORITY**

Preview -> share tab audio -> Arm -> Confirm -> verify signal -> Restore

**HEALTH**

Diagnostics or Health -> run checks -> resolve required red items -> re-run

**REMEMBER****The golden rule**

Select, act, verify. If the visible result is not the expected result, stop clicking and open the readiness page.